



TRIANGULAR  $\mu$ OS 1.27

for

 **Commodore**  **64**

User's Manual

© 2023

## Contents:

### PART A: PREPARATIONS

1. Introduction	4
2. What's new	5
3. What you need, Support & Legal note	6

### PART B: HOW TO USE TRIANGULAR $\mu$ OS

4. How to use TRIANGULAR $\mu$ OS 1.27	8
--	---

### APPENDICES

A. Troubleshooting	14
B. Support & References	15

## PART A

# PREPARATIONS

# 1. Introduction

TRIANGULAR  $\mu$ OS is GUI (graphic user interface) operating system for 8-bit Commodore computers. This User's Manual pertains to TRIANGULAR  $\mu$ OS 1.27 version for Commodore 64.

Package contains files:

- ***TRIANGULAR  $\mu$ OS 1.27 for Commodore 64 Users Manual.pdf*** – this manual
- ***TRIANGULAR  $\mu$ OS 1.27.d64*** – image of TRIANGULAR  $\mu$ OS System Disk containing 4 files, which take 39.98 KB (164 disk blocs = 41.00 KB on disk)
- ***TRIANGULAR  $\mu$ OS 1.27 SYSTEM DISK*** – folder containing all System Disk files for convenient use with SD2IEC
- ***TRIANGULAR  $\mu$ OS 1.27 Documents.d64*** – empty formatted  $\mu$ OS Documents disk image for storing your documents

Goal of creating this system was to develop GUI for 8-bit Commodore computers with lowest amount of memory: that is Commodore PET with at least 4 KB of memory. Next it was expanded for Commodore VIC-20 with standard 5 KB of memory and in later versions higher amount of RAM was required. This iteration of TRIANGULAR  $\mu$ OS (version 1.27) requires Commodore 64.

This software was written in Commodore BASIC language (port of Microsoft BASIC) using CBM prg Studio 4.1.0, and is designed to run on standard Commodore 64. TRIANGULAR  $\mu$ OS is designed to support BASIC 2.0 (alternatively named BASIC V2) and works in color text mode. Commodore BASIC (a runtime interpreted language similar in basic concept to JAVA RTM or C# CLI) is default language used in 8-bit Commodore computers and also functions as their OS and user interface. Similarly, to early Microsoft Windows (1.0 to 3.11),  $\mu$ OS sits atop of BASIC and KERNAL (Commodore's kernel) and Commodore DOS. It uses Commodore DOS implemented in Commodore disk drives or 3<sup>rd</sup> party solutions in order to load its parts, load/save settings and documents, perform operations on floppy disks and communicate with disk drive(s).

## 2. What's new

### What's new in TRIANGULAR $\mu$ OS 1.27 for Commodore 64:

- Filenames convention changed from filename>ext[ension] to standard filename.ext[ension]  
e.g. uos>cfg to uos.cfg
- Added SYSTEM DISK folder for use with SD2IEC
- GUI: Menu Start button in the center of taskbar now made from purple TRIANGULAR logo
- WORDS: file extension changed to .txt
- MONITOR simplified running Machine Language program function
- STAR WARS X-Wing vs TIE Fighter (based on PET version) in place of CHUCK CHALLENGE
- CHUCK CHALLENGE added as extra on System Disk
- Various other bugfixes and improvements

### 3. What you need, Support & Legal note

In order to run TRIANGULAR  $\mu$ OS 1.27, you need real Commodore 64 with disk drive and joystick to operate cursor. Printer is optional and can be used as device #4 to #7, although #4 is standard practice and thus recommended.

You can also use freeware VICE emulator, which is available here:  
[vice-emu.sourceforge.io](http://vice-emu.sourceforge.io)

Commodore 64 emulator VICE must be configured with enabled disk drive that can read 170KB 5.25" diskette (.d64 file): recommended CBM 1541 or 1541-II (default). Also, you should enable joystick in port 2. You can easily configure it as Numpad keys:

- Up (8), Down (2), Left (4), Right (6)
- You can move diagonally e.g., Up-Left (7)
- 0 or right Ctrl: Fire (click/select)

You can also enable printer in VICE emulator. Do this in:  
Settings -> Peripheral devices -> Printers or similar options. You can choose printer as device #4 - #7, although #4 is standard and recommended.

#### **SUPPORT:**

More information about TRIANGULAR  $\mu$ OS for Commodore 64 or other computers system is available on TRIANGULAR  $\mu$ OS website, where you can download SDK, report bug or get help:  
[triangular-uos.blogspot.com](http://triangular-uos.blogspot.com)

#### **LEGAL NOTE:**

TRIANGULAR  $\mu$ OS is free and open software which you can freely copy, share and edit but give credit to creators of  $\mu$ OS (especially 3rd party games creators).

## PART B

# HOW TO USE TRIANGULAR $\mu$ OS

## 4. How to use TRIANGULAR $\mu$ OS 1.27

To start using TRIANGULAR  $\mu$ OS insert TRIANGULAR  $\mu$ OS 1.27.d64 disk into disk drive and type command: LOAD “\*”,8 or LOAD “UOS”,8 in BASIC and press Return key (or Enter on PC keyboard in case of emulators). System launcher named UOS will check your system. If you are using your drive as device #8, use one of above commands. If you are using different device # then change last number (8) to it (e.g.: LOAD “\*”,9 if you want to use disk drive #9). After successfully loading startup program type RUN (and press Return/Enter) to start  $\mu$ OS.

Now system starts. BIOS is first element of this system. It checks if running machine is indeed Commodore 64 computer, check memory available and checks screen memory. In this stage, if any of above system checks weren't finished successfully,  $\mu$ OS will display error message, beep 3 times and return to default BASIC mode.

Next  $\mu$ OS BIOS proceeds to launchings screen and checks if there are any disk drives, detects their hardware IDs, and if system disk is present, automatically sets boot drive to lowest disk drive # containing matching system disk and load configuration file. If there isn't proper TRIANGULAR  $\mu$ OS System Disk inserted in any of disk drive or disk drive has not been detected, beep sound and error message will be displayed (along with sound of 3 beeps) with possibility to retry detection procedure (F1) or exit to BASIC (F8).

If everything went OK, F1 BIOS SETUP option will appear. By pressing F1 key, you can enter BIOS SETUP menu, where system parameters and list of detected disk drives will be presented. To change Boot Drive or Work Drive hit highlighted key (F1 - F8) displayed after name of available disk drive\*. You can also change system time by using T key and entering new time in format HHMMSS left of white arrow or reset system clock by hitting R key. To continue without saving changes (besides time clock which is changed independently) and go back to launch screen press E key. To save changes and restart  $\mu$ OS use S key. By pressing B key computer shuts down  $\mu$ OS completely by going into standard BASIC mode. When F1 key is not pressed when launching screen is present, BIOS continues to launching GUI.

\* If you have another disk drive enabled, you can insert TRIANGULAR  $\mu$ OS 1.27 Documents.d64 or any other disk into second drive and in BIOS Setup menu change Work Disk to that drive number (most probably #9). By doing this you can easily load/save documents on separate disk from TRIANGULAR  $\mu$ OS System Disk (which is recommended setup). Otherwise, you will load/save documents from System Disk (unless you will change disk while working in WORDS word processor), which is default option (Work Disk is set as #8 or other device # of Boot Drive if #8 is not available).



GUI (graphic user interface) is central element of TRIANGULAR  $\mu$ OS. GUI's is operated by arrow-like mouse pointer which is joystick navigated:

- Up, Down, Right, Left [(or 2,4,6,8 on Numpad in emulator)]
- You can move diagonally (e.g., Up-Left [or 7 on Numpad in emulator])
- Fire to select/click [or 0 / right Ctrl in emulator]

On bottom of the screen there is task bar with TRIANGULAR logo on center and digital clock on the right side with up arrow symbol to right of the clock. By clicking on this arrow, you will be able to go back directly to initial desktop screen from future windows (this is very useful when you want to skip closing previous windows).

By clicking on TRIANGULAR logo, you will open start menu where you can select:

- SETTINGS – opens SETTINGS window
- RESTART – restarts TRIANGULAR  $\mu$ OS
- SHUT DOWN – exits to standard BASIC mode

On main screen desktop there are 4 icons:

- THIS C64 – open window similar to My Computer or This PC in Windows
- APPS – opens folder with selection of apps
- GAMES – opens folder with games
- SETTINGS – opens SETTINGS window

SETTINGS window is divided on two tabs: SYSTEM and GRAPHIC. SYSTEM tab allows you to change system time (by clicking on + and – signs to change hours, minutes, seconds). Click on RESET CLOCK button to reset system clock. Below label WORD DISK there are buttons with device # (8> to 11>) on them. Red color of those buttons indicate that device is unavailable. Cyan color marks available drive and green show current selected work drive. Clicking on cyan button will change Work Drive to it. Below of PRINTER label there are buttons to select printer device # (NO, #4 - #7). If NO button is selected (default) no port is assigned and printing functions are not available in TRIANGULAR  $\mu$ OS apps (e.g., WORDS). Most popular setup is to use printer as device #4. APPLY button saves selection into config file. As in most GUIs clicking on X button closes the window. By doing so without saving, any changes (besides time) are canceled.

GRAPHICS tab enables color options. By clicking on one of 16 tiles on right of BACKGR PATTERN label you can change desktop wallpaper pattern. COLOR offers selection of colors for background wallpaper. REVERSED will turn reverse of wallpaper patten off/on (enabled with first pattern will change it to solid color). TITLE BAR will change color of title bar of windows. DEAFULT button brings default color theme. Don't forget to click on APPLY button to save color changes or exit this window without saving them to discard changes.

THIS C64 window contains 2 icons:

- DISK – open program which shows content of disk and starts programs stored on it
- CMD – starts a command prompt program

DISK is a program for viewing disk content. Right of status info with number of files on disk and current page there are buttons with device # (8> to 11>) on them. Red disk button indicate that device is unavailable. Cyan color marks available drive and green show current selected drive. Clicking on cyan/green button will start displaying disk content (on start program will display content of disk inserted in Work Drive). Further below is displayed disk name and disk ID. When there no disk in disk drive or disk is empty (not formatted) program will display message: NO DISK! While program retrieves disk content directory from disk drive CHECKING DISK... F8 ABORT label is displayed and pressing F8 key aborts disk checking procedure. Further down there is field for disk content listing, which will display 10 items per page. In both bottom corners of window there are 2 arrows: > (on right) and < arrow (on left) will change page if additional program pages are available. Clicking on program from that list will start it.

CMD is a DOS-like command prompt program that allows you to manage disk content. It accepts one of following commands (disk and file names cannot be longer than 16 characters):

- HELP – shows help
- CLR – clears screen
- EXIT – go back to desktop
- RESTART – restarts TRIANGULAR  $\mu$ OS
- BASIC – restarts computer to BASIC
- & – displays basic system info
- ! – displays current device info
- #[devide number] – changes disk drive: #1 for Datasette, disk drives 8-11 e.g.: #1, #8, #11
- \$ – show directory (content) of disk
- ↑[filename] – load program e.g.: ↑SIMCITY
- ↑ – load first encountered program (similar to LOAD “\*”,8 in BASIC)
- S>[filename ] – deletes file e.g.: S>SIMCITY
- R>[old name]=[new name] – renames file e.g.: R>OLD NAME=NEW NAME
- C>[original file]=[new file] – copies file e.g.: C>ORIGINAL FILE=NEW FILE
- N>[disk name<id] – formats disk (ID must be 2 charters long) e.g.: N>DISKNAME<ID
- D>[0]=[1] – make backup copy on double disk drives
- I> – initialize disk
- V> – validates disk

If any of above command will be entered erroneously or with improper parameter(s) error message INVALID COMMAND! or BAD PARAMETER! will be displayed alongside with beep sound. After any operation user will be informed of its success (message: OK ✓) or descriptive error message will be displayed.

APPS folder contains 4 programs: WORDS, MATH, MONITOR and SYNTH.

WORDS is a word processor. Use Cursor Up or Cursor Down/Return to scroll page. Shift + Return to discard changes in current line and advance to next line. All operation evoked by function keys beside F5 (F1-F4 and F8) will pop up confirmation Yes/No prompt. Press F1 to start new file. F2 prints document on printer (you must have printer assigned to any port [#4 - #7] in SYSTEM tab of SETTINGS, before printing otherwise F2 key won't enable printing function). Use F3 key to load document and F4 to save current document to file. F5 inserts tabulation of 10 spaces. F6 key will copy line to clipboard, while F7 will paste copied line or number copied to clipboard in MATH calculator to current line. Pressing HOME key will get you to beginning of document and SHIFT + HOME will delete clear current line. Exit by pressing F8.

MATH – scientific calculator. To add 2 numbers, enter 1<sup>st</sup> number (by keyboard or by cursor by clicking on numbers in purple/blue field). Entered number will appear on right from B label. Use left arrow button or DEL key to delete 1 digit. Reset B register by clicking on C button or pressing C key. Click on = or + button or press = or Return key to store number from B register in A register. Next similarly add 2<sup>nd</sup> number and then click on any desired operation button or press +, -, \*, /, % keys. Result will be showed in A register (above B register). Other mathematical functions operate similarly: enter 1 or 2 numbers and then press button with given function. Pi button (with  $\pi$  symbol on it) stores  $\pi$  value in register B. Click ON or press O key to reset calculator state. Clicking on A<>B button will swap numbers in registers A and B. A>M will store value of A register in clipboard. M>A button will store number saved to clipboard either in MATH or WORDS program. MC will erase clipboard.

MONITOR is a program that shows and edits computer memory. Memory cells values are displayed in hexadecimal number system (0-F). Possible commands:

- HELP – shows help
- CLR – clears screen
- EXIT – goes back to APPS folder
- E>[address] – change memory from given memory address, one byte after one byte (in prompt type X to cancel, you can type R to repeat previous byte value)
- M>[address] – shows memory block of 256 bytes containing given memory address
- F>[1<sup>st</sup> address]-[2<sup>nd</sup> address]=[byte] – fills specified memory region with given byte value
- T>[1<sup>st</sup> address]-[2<sup>nd</sup> address]=[destination address] – copies specified memory region to another
- S>[1<sup>st</sup> address]-[2<sup>nd</sup> address]=[start address of other region] – swaps specified memory region with another
- G>[address] – executes machine language program starting at address

SYNTH is sound synthesizer program. F1 and F2 keys will lower/rise volume (which is represented by green volumeter). Use keys showed on keyboard scheme to play sound in normal octave. Pressing those keys while holding SHIFT will play them in higher octave, while holding C= key will play them in lower octave. Use SPACEBAR to stop playing sound. Pressing function keys F3 - F7 will change voice characteristic. Use F8 key to exit.

GAMES folder offers 4 game titles:

- SIMCITY – create and develop your city. Move cursor by joystick and press R, C or I key to place Residential, Commercial or Industrial zones. Use Space to build a road. Roads are essential since only land plots with road adjacent to them can further develop into occupied one and bring revenue to the city
- STAR WARS X-Wing vs TIE Fighter – fabulous Star Wars themed space shooter. Shoot down 20 TIE Fighter to discover Darth Vader greatest secret.
- TAXI TAXI – Drive your taxi cab (yellow square) to citizen (yellow (dot) that is not moving longer time to pick him up. Drive passenger to building pointed by cyan arrow. Running over moving citizens ends game. Transport 9 passengers to win game.
- LIFE RAFT RESCUE – Fly Rescue helicopter to gather survivors. Go back to white rescue ship to refuel. Once fuel tank is empty game is over.

One extra game is on System Disk and can be opened from CMD (^CHUCK) or DISK program by clicking on CHUCK program to run it:

- CHUCK CHALLENGE – help Chuck Peddle raise money for development of 6510 CPU by jumping through platforms and collecting golden coins

# APPENDICES

## A. Troubleshooting

Loading of next module of TRIANGULAR  $\mu$ OS can “freeze” in process of inter-loading next  $\mu$ OS module or disk program (very rare occurrence). This happens when loading screen not proceeds to next module for over 2 minutes for  $\mu$ OS (smaller program will take less time to do so). When loading screen is not responsive for longer time, it means error in inter-loading procedure, most probably keyboard buffer was not filled with key properly. To see what really happened change color of cursor to blue (press Control + 7) and enter command POKE 53281,1 and hit Return key. This should change background color to white which will show underlying black text of loading sequence. If computer doesn't change cursor or background color try again. If still there is no effect it might be real freeze. If color change procedure succeeds, try using RUN command to see if program will start or go to top of screen (Home key) and press Return in order try to reload program. If it will loads successfully enter RUN command. If that not work check if load command is correct. It should have format: LOAD “[filename]”, [device # (1 or 8 - 11)] like in e.g.: LOAD “GUI”, 8. If none of it works then start system anew. To prevent this kind of freeze, try not to use keyboard when inter-loading procedure is performed (it can slip improper key into keyboard buffer, which most often leads to this error).

## B. Changelog

**TRIANGULAR  $\mu$ OS 1.27 for Commodore 64 [29-09-2023]:**

- Filenames convention changed from filename>ext[ension] to standard filename.ext[ension]  
e.g. uos>cfg to uos.cfg
- Added SYSTEM DISK folder for use with SD2IEC
- GUI: Menu Start button in the center of taskbar now made from purple TRIANGULAR logo
- WORDS: file extension changed to .txt
- MONITOR simplified running Machine Language program function
- STAR WARS X-Wing vs TIE Fighter (based on PET version) in place of CHUCK CHALLENGE
- CHUCK CHALLENGE added as extra on System Disk
- Various other bugfixes and improvements

## **TRIANGULAR $\mu$ OS 1.25/C64 for Commodore 64 [20-10-2022]:**

- Code of TRIANGULAR  $\mu$ OS is reviewed, improved, cleaned and bug fixed
- System Registry is rearranged to make space for 2 sprites
- Slightly updated loader module screen (LOADING/RESTARTING/SHUT DOWN)
- Multi-characters handled by special function amounted for saving 1 KB of code
- BIOS: Some minor visual changes (mostly colors)
- BIOS: Detection of C64 or C128 in C64 mode
- GUI: Mouse pointer uses sprite instead of PETSCII character
- GUI: Time separator : (in right bottom corner) is blinking as seconds progress
- GUI: Windows repositioned and stretched with minor visual changes
- GUI: Windows can activate elements outside their loops in more advanced manner
- GUI: First element of  $\mu$ OS API named BASICCALLY added: Window creator that draws window based on given arguments
- GUI: Windows refreshes faster and without blinking
- SETTINGS: System settings and color settings merged into one SETTINGS window, divided by 2 tabs into SYSTEM and GRAPHICS (color options)
- SETTINGS: GRAPHICS tab now supports 16 colors and 2x more background patterns
- DISK: Program window slightly enlarged and improved few minor mechanisms
- CMD: Small visual changes and improved few minor mechanisms
- WORDS: Commands panel slightly redesigned with new options added
- WORDS: Repositioned and expanded text area
- WORDS: > symbol (indicating line to write) is removed and text area is 1 character wider
- WORDS: Faster typing-in mechanism
- WORDS: Clear Screen [Shift + Home] erases currently written line
- WORDS: F6 Copy line and F7 Paste line added
- WORDS: Clipboard shared with MATH calculator (F7 will retrieve memorized number in MATH)
- MATH: Window repositioned and minimal color theme update
- MATH: Clipboard shared with WORDS word processor (memory contains number copied inside WORDS)
- MONITOR: Show memory area function is reworked and enlarged
- SYNTH: Piano keyboard expanded and new voices added
- SIMCITY: Mechanism that selects land plot to activate is more random and equally covers available zoning area
- GAMES: CHUCK'S CHALLENGE & LIFE RAFT RESCUE - issues with sprites are corrected



### **TRIANGULAR $\mu$ OS 1.20/C64 for Commodore 64 [31-08-2022]:**

- Supports Commodore 64 with its 40 column VIC-II text mode and SID chip
- BIOS: added indicator reminding to type time (<- TYPE NEW TIME) after pressing T
- WORDS: by pressing HOME key you can reach first line of document
- SYNTH is reworked with simplified keyboard and limited to 1 voice channel which now can play sounds in normal, lower and higher octave ranges
- Only 1 game: SIMCITY is carried over from TRIANGULAR  $\mu$ OS for Commodore VIC-20
- 3 new games from Roman Werner are added in place of old games:  
TAXI TAXI, CHUCK'S CHALLENGE and LIFE RAFT RESCUE
- All games merged into GUI program file
- Bugfixes and improvements